

# autobrr

autobrr is the modern download automation tool for torrents.

- [autobrr](#)

# autobrr

For information regarding autobrr, visit the [autobrr website](#).

## Connection Details

The connection details for each client in `Settings -> Clients` is given below.

### qBittorrent

```
Host: https://{username}.{servername}.usbx.me/qbittorrent
TLS: Enabled
Username: {username}
Password: qBittorrent's Password as given in your Control Panel
Basic auth: Disabled
```

### Deluge v1

```
Host: {servername}.usbx.me
Port: Deluge's Daemon Port as given in your Control Panel
TLS: Disabled
Username: {username}
Password: Deluge's Password as given in your Control Panel
```

### Deluge v2

```
Host: {servername}.usbx.me
Port: Deluge's Daemon Port as given in your Control Panel
TLS: Disabled
Username: {username}
Password: Deluge's Password as given in your Control Panel
```

### rTorrent

```
Host: https://{username}:{ruTorrent Password}@{username}.{servername}.usbx.me/RPC2
* The ruTorrent password can be found in your Control Panel
```

### Transmission

Host: {servername}.usbx.me  
Port: Transmissions' RPC Port as given in your Control Panel  
TLS: Disabled  
Username: {username}  
Password: Transmission's Password as given in your Control Panel

## Radarr

Host: https://{username}.{servername}.usbx.me/radarr  
API Key: Radarr's API Key found in Settings -> General -> Security  
Basic Auth: Disabled

## Sonarr

Host: https://{username}.{servername}.usbx.me/sonarr  
API Key: Sonarr's API Key found in Settings -> General -> Security  
Basic Auth: Disabled

## Lidarr

Host: https://{username}.{servername}.usbx.me/lidarr  
API Key: Lidarr's API Key found in Settings -> General -> Security  
Basic Auth: Disabled

## Readarr

Host: https://{username}.{servername}.usbx.me/readarr  
API Key: Readarr's API Key found in Settings -> General -> Security  
Basic Auth: Disabled

## SABnzbd

Host: https://{username}.{servername}.usbx.me/sabnzbd  
TLS: Enabled  
API Key: SABnzbd's API Key found in Settings -> General -> Security  
Basic Auth: Disabled

# Add Prowlarr Indexer Feed

- Begin by navigating to your Prowlarr webUI.

- In your Indexer list, right-click the Feed icon and copy the URL to your clipboard. As shown in the below image.

- The URL will look like this:


`https://username.hostname.usbx.me/prowlarr/1/api?apikey=839dktue43424ac8b9301313d23e0d9d&extended=1&t=search`

- The following section is your **Feed URL**:

`https://username.hostname.usbx.me/prowlarr/1/api`

- The section between `apikey=` and `&` is your **API Key**, which in this example would be:

`839dktue43424ac8b9301313d23e0d9d`



- Next, navigate to the autobrr webUI, go to **Settings > Indexers** and click the `+ Add New Indexer` button.
- In the Indexer dropdown list, choose **Generic Torznab**.
- Next, type into the following text fields:
  - **Name:** Set a name of your choice
  - **Torznab URL:** Paste the Prowlarr Feed URL that you previously copied, make sure to only paste the Feed URL section, as mentioned previously.
  - **API Key:** Paste the API Key from the previous Feed URL.
  - **Download type:** Choose Torrent
- Lastly, click the **Save** button in the bottom right corner.
- Done!

## View Logs

- The autobrr logs are located in the directory `/home/{username}/.apps/autobrr/log`.
- The latest log entries can be viewed using the following command via [SSH](#):

```
tail -f ~/.apps/autobrr/log/autobrr.log
```