

Recyclarr

This unofficial app installation script is provided for your convenience. The script is provided as-is and may not be updated or maintained by Ultra.cc. Clients are welcome to use and customize unofficial app installers for their unique needs and requirements. Unofficial support may be offered via [Discord](#) only and at the sole discretion of Ultra.cc staff. Use at your own risk and only proceed if you are comfortable managing the application on your own.

Recyclarr is a command-line application that will automatically synchronize recommended settings from [TRaSH guides](#) to your Sonarr/Radarr instances.

- Official documentation for Recyclarr can be found [here](#).

Installation

- Connect to your Ultra.cc service via [SSH](#)
- Once connected, execute the following command:

```
bash <(wget -q0- https://scripts.ultra.cc/main-v2/Recyclarr/main.sh)
```

- Next, to install Recyclarr, press `1` and `ENTER` to confirm.
- Done!

Configuration

Before you can start using Recyclarr, you need to create at least one YAML configuration file. By following the below instructions, a minimal configuration file will be created at `~/.apps/recyclarr/recyclarr.yml`. In this guide, we will only show the bare minimum needed to set up Recyclarr. For more information regarding configuration, see the [wiki](#).

- Create `recyclarr.yml` by executing the following command:

```
recyclarr config create
```

- Next, to edit the configuration file, execute the following command to open `recyclarr.yml` in the Nano editor.

```
nano ~/.apps/recyclarr/recyclarr.yml
```

- Next, edit `base_url` and `api_key` for Sonarr/Radarr. See below example:

```
base_url: https://username.hostname.usbx.me/radarr
```

```
api_key: <YOUR_API_KEY_HERE>
```

- Make sure to replace `username` and `hostname` with your specific username and hostname.
- Also, make sure to set the correct Base URL for each section, e.g `/radarr` for the Radarr section, and `/sonarr` for the Sonarr section of the configuration file.
- Lastly, replace `<YOUR_API_KEY_HERE>` for each section. The API key can be found in **Settings** > **General** in the webUI of Sonarr/Radarr.

At this point, the bare minimum needed for Recyclarr to work has been done, but before you run `recyclarr sync` we recommend that you do your own research and thoroughly read the [Recyclarr wiki](#).

Uninstallation

- Connect to your Ultra.cc service via [SSH](#)
- Once connected, execute the following command:

```
bash <(wget -qO- https://scripts.ultra.cc/main-v2/Recyclarr/main.sh)
```

- Next, to uninstall Recyclarr, press `2` and `ENTER` to confirm.
- Done!

Revision #8

Created 23 October 2023 08:36:10 by varg

Updated 24 August 2024 16:51:23 by varg